TN.h — Arduino Library for Tangible Networks TN-04

Espen Knoop

This is an Arduino library for use with Tangible Network TN-04 nodes. It handles inputs, outputs, reading switches etc. For serial communication, use the standard Arduino functions.

The library defines a class TN, so using it requires creating a TN object and calling its methods. Here is a minimal example of use:

```
#include<TN.h> // Requires TN.h, TN.cpp, Keywords.txt in folder <Arduino>/Libraries/TN/
TN Tn = TN(-1.0,1.0); // Create TN object with range [-1.0, 1.0]
void setup () {} // Don't need anything in here - inputs/outputs set up in constructor
void loop () {
   Tn.colour(255,255,255); // Set LED to white
   delay(500);
   Tn.colour(0,0,0); // Set LED to off
   delay(500);
}
```

Nodes have 3 inputs and 3 outputs. Inputs/outputs are numbered 1-3 so as to be in keeping with labels on the PCB/units. Nodes also have a pot (potentiometer, knob), a pushbutton switch and 3 DIP configuration switches that can be switched with a small screwdriver or similar.

Most models will probably use analogRead() and analogWrite(), but digitalRead() and digitalWrite() are also provided for models requiring only binary information (on/off) to be sent between the nodes.

The library defines the following methods:

```
TN(double minVal=0.0, double maxVal=1.0)
                                                  Constructor for TN object. Input arguments specify range
                                                  of analogRead() and analogWrite(): values outside range
                                                  will be clipped. If arguments are not specified, range is set
                                                  to [0.0, 1.0].
                                                  Set LED colour. Integer arguments \in [0, 255].
void colour(int r, int g, int b)
void colour(double r, double g, double b)
                                                  Set LED colour. double arguments \in [0.0, 1.0]
                                                  Returns true if input is connected, false otherwise.
boolean isConnected(int input)
double analogRead(int input)
                                                  Read the value of an input. Returns minVal if input is not
                                                  connected.
void analogWrite(int output, double value)
                                                  Write a value to an output. Value is clipped if outside
                                                  [minVal,maxVal] range.
int digitalRead(int input)
                                                  Read the value of an input as true or false. Only use in
                                                  conjunction with digitalWrite().
void digitalWrite(int output, int value)
                                                  Write an output to true (maxVal) or false (minVal).
                                                  Get state of DIP switch 1 (true is on).
boolean dip1()
boolean dip2()
                                                  Get state of DIP switch 2 (true is on).
boolean dip3()
                                                  Get state of DIP switch 3 (true is on).
boolean sw()
                                                  Get state of pushbutton switch (true is pressed).
double pot()
                                                  Get position of pot. Returns double between 0.0 (fully
                                                  CCW) and 1.0 (fully CW).
boolean masterConnected()
                                                  Returns true if master controller is connected.
                                                  Get value of master controller. Returns double between
double masterRead()
                                                  0.0 (fully CCW) and 1.0 (fully CW). Returns 0.0 if master
                                                  controller is not connected.
boolean masterSw()
                                                  Returns true if master switch is pressed. Returns false
                                                  if master switch not connected. Do not combine with
                                                  masterRead().
void printState()
                                                  For debugging. Prints out the current state (ins, outs,
                                                  switches etc) to serial. Requires Serial.begin(115200)
                                                  in setup(). Runs in approx. 5 ms.
```

The libary also includes fast functions for max and min, MAX(x,y) and MIN(x,y), as well as MINMAX(x,l,u) which returns x if l < x < u, l if x < l and u if u < x.